


GIS Centre Top 10 Tools

Dissolve for ArcPro


Aggregates features based on specified attributes. It removes internal boundaries



INPUT

OUTPUT

Where is it located?



Go to the **Analysis** ribbon tab at the top of the screen, and scroll down to find the **Dissolve** tool, OR, click on the Tools button and search **Dissolve** in **Geoprocessing** Pane

Parameters:

Input Features – The features to be aggregated.

Output Feature Class – The data that is created.

Dissolve Field(s) – The field(s) on which to aggregate features. If value in the field are the same the data is aggregated together.

* If nothing is specified then all internal boundaries are removed.

Statistics Field(s) – Choose the statistics and fields with which to summarize aggregated data. Text attribute fields can be summarized to the First or Last. Numeric fields may be summarized using any statistic. Null values are excluded from all calculations.

First – Finds the first record in the Input table and uses its specified field value. (Best used for "Text" data)

Last – Finds the last record in the Input Table and uses its specified field value. (Best used for "Text" data)

SUM – Adds the total value for specified field. (Only works on numeric data)

MEAN – Calculates the average for the specified field. (Only works on numeric data)

MINIMUM – Finds the smallest number for all records in the specified field. (Only works on numeric data)

MAXIMUM – Finds the largest value for all records in the specified field. (Only works on numeric data)

RANGE – Finds the range of values (MAX – MIN) for the specified field. (Only works on numeric data)

STANDARD DEVIATION – Finds the standard deviation on the value in the specified field.

COUNT – Finds the number of values included in the statistical calculation. This counts each value except null values. (Hint: to find the number of Null values use count on another field that has no nulls and subtract the 2 values.)

MEDIAN - Calculates the median for all records of the specified field.
(Only works on numeric data)

VARIANCE - Calculates the variance for all records of the specified field.
(Only works on numeric data)

Create Multipart Feature - Specifies if multipart features are allowed in output feature class (1 record in table but potentially multiple polygons). The default is checked. (Recommend unchecking this feature to have a 1-1 relationship between records and polygons)

Unsplit Lines – Only applies if input features are lines. Controls how line features are dissolved. Unchecked the lines are dissolved into a single feature (default). Checked the lines only dissolve when two lines have a common end vertex.